

English user manual

Re:control

M230_{WIN} App

E2.3.0

REVOX


Dominating Entertainment.
Revox of Switzerland.

Content

- General 1**
 - M230 display options..... 2
- System Requirements 3**
- Installation..... 4**
 - Carry out basic settings..... 5
 - Connection Setup 6
 - M230 with network integration..... 7
 - Multiroom System with slave connection..... 9

General

The Re:control M232 Application (App) for Windows products facilitates the comprehensive operation of the complete Revox Multiroom System. Select the room and operate the various Revox Multiroom System sources with the direct-dial keys. Using the App, the state of the various sources is shown to you in realtime.



As well as the operation on the musical side, you can of course also set up the individual timers in your rooms and if the Setup button is displayed, you can carry out the basic configuration of your Revox equipment.

In this way, you can select and play your favourite music, which you have stored on your Revox Audio Server. In the same way, you can have full two-way operation of the Multimedia module, enabling you to access the various sources offered by this module. It doesn't matter whether you are enjoying a program on Internet radio or whether you want to select music from you network hard drive.



M230 display options



Display of the currently selected (Music) source in the main room. As well as the information display in the centre of the display, the specific control softkeys from the corresponding sources are also shown.



Timer function display. This function is available if a Multiroom (sub-) module is installed in the Re:system device.



Re:system M100 amplifier menu The basic settings for the amplifier part are made here, including the specific adaptation to the Revox Re:sound speakers.



Amplifier menu from the M219 Side-room amplifier – “Sideroom”. The sound settings can be adjusted individually for each side room.

System Requirements

System requirements for controlling the Revox equipment via:

Ethernet

-  Revox Re:system M10 with **integrated Ethernet interface**
or
Revox Re:system M51/ M100 [Slave] with **external M202 Ethernet interface**.

-  The M10 or M202 Ethernet interface must already be connected with your Ethernet network and must be configured.

-  The complete Multiroom system must have the V2.00 system software, or higher.

USB

-  Revox Re:system M10 / M51 Mk2/ M100 with integrated USB interface on the back of the device.
Note: An M51 Mk1 (SN < 3000; red standby LED) does not have a USB interface and therefore, cannot be controlled by USB.

-  The complete Multiroom system must have the V2.00 system software, or higher.

Serial via RS232

-  Revox Re:system M10 with **integrated RS232 interface**
or
Revox Re:system M51/ M100 with **external M200/ M203 RS232 interface**.
Setting *Serial Port mode RS232 Link*

-  The complete Multiroom system must have the V2.00 system software, or higher.

Installation

When installing the Re:control M230, the Revox equipment should not yet be connected to the computer.

Double-click on the *Revox_M230_Setup_32_64.exe* file. If no other path is defined for the installation, the M230 folder is in the path `c:\Program Files\Revox`.

The M230-App can only be operated with a Windows PC and supports Win XP, Win Vista and Win 7 in the 32- and 64-bit versions.

Follow the installation routine and only carry out the recommended USB driver installation at the end, if you are planning to operate your Revox equipment later by USB.

Once installation has been completed, the connection settings can now be made - see next chapter.


USB connection

If control should be done by USB, a Re:system device (M10, M51 Mk2, M100) will be connected with the computer by USB after the installation of the M230. This step completes the driver installation. Otherwise, under certain circumstances, there could be errors with the FTD2XX.DLL file.



Options during the installation:

- Create Desktop icon
- All program to the Autostart folder



Options during the installation:

- Install Revox USB driver (recommended)
- Start Revox M230 terminal

Note for MAC users

If you have MacOS installed on your computer, you can use the **Re:control M234** App from Revox in the same way as the M230.

Carry out basic settings

After the program has been installed, a **V** icon appears in the Status bar on the bottom right of the screen.



Right-click on the **V** icon. Now select the **Setup** option.

You can make essential settings through this overview window.



Stay On Top

The M230 window always stays on the top screen layer regardless of whether new programs are opened.

Start Maximized

Currently this has no function.

Default Position

If this checkbox is activated, the M230 window always appears bottom right on the screen. If the checkbox is cleared, the M230 remembers its last position appears there again next time it is started.

Show Setup Button

If this checkbox is activated, a *Setup* button appears in the M230 menu if "Main Room" is chosen from the room selection. With all other rooms, a *Local* button is display regardless of this function setting.

Size (Small – Medium - Large)

Here you select the size of the M230 window.

Default Room

In the case of a Revox Multiroom System with several side rooms, the preferred room can be selected here that should be displayed when the M230 is started.

Connection

Calls the Setup window for the connection settings between the computer and the Revox equipment. See next page for description.

Connection Setup

The access type and its specific settings are selected here. You will find the system requirements for this on Page 3.

Serial Port

Connection via serial RS232.

Directly available in the case of a Re:system M10 or over a Re:connect M200 and M203 interface, which is connected with a Re:system device.

USB Link

Connection via USB.

Cable type: USB A → B


Available in the case of Re:system M10, M100 and M51 Mk2*

TCP/IP (recommended for M230)

UDP/IP

Connection over a network - Ethernet
As the Revox Ethernet interface doesn't support DHCP, the IP address has to be entered directly. You will find a detailed description of how to find out the interface IP address on Page 7.

Directly available in the case of a Re:system M10 or over a Re:connect M202 Ethernet interface, which is connected with a Re:system device**.



Important notes

* M51 Mk2 can be recognised from the **blue** standby LED. (M51 Mk1 = **red** LED)


** In a Multiroom System with integrated slave devices (Re:system M51 Slave, M100 Slave), each of the slave devices also requires its own M202 Ethernet interface as well as the main device (Re:system M51, M100).

However, only the IP address of the main device (Multiroom central unit) is entered in the *Connection Setup*. The IP address of the slave devices is/are automatically determined by the Multiroom cabling of the M230.

M230 with network integration

Reading out Revox IP address

In order to be able to use the M230 App in an Ethernet network, you have to read out the **IP address** of the Revox Ethernet interface and enter it in the Re:control M230 *Connection Setup* menu.



Depending on the Re:system model, there are different ways of finding out this IP address.


- For Re:system M10
- For Re:system M15/ M100

• I have a Re:system M10


There is no display with an M10 system that allows you to directly read out the IP address of the integrated Ethernet interface.

Connect your computer via USB to the M10 and select the option **USB Link (M10)**. in the Connection Setup.

If you now start the M230 and call the Setup on the M10 (activate the Setup button in the Re:control M230 - see Page 5), you can call the TCP/IP menu using the **Ethernet** softkey and read out the M10's assigned IP address there.



Press the **Menu** softkey on the first page (Client List). The second **TCP/IP Setup** page appears.




Note down the IP address (192.168.120.200 in this example) and now enter this in the M230's *Connection Setup* [TCP/IP].

• *I have a Re:system M51/ M100*

If you have a Re:system M51/ M100, you can read out the IP address of the connected **M202** Ethernet interface directly on the M51 or M100 display.

Reading out using an M202

Switch the M51/ M100 on using the **Power** button on the front of the unit. Now press the small Setup button on the M202 Ethernet interface.



Note down the IP address (192.168.120.200 in this example) and now enter this in the M230's *Connection Setup* [TCP/IP].





Fig.: M202 with Setup button

The following appears on the M51/ M100 display:



If you now press the **Menu** key in the display, the second **TCP/IP Setup** page appears

Multiroom System with slave connection



Control of a Multiroom Slave system with the Re:control M230

In a Multiroom System with a Re:system M100 Slave device, the slave device also requires its own M202 Ethernet interface as well as the main device). However, only the IP address (here 192.168.0.5) of the main device (Multiroom central unit) is entered in the *Connection Setup*. The IP address of the slave device (here 192.168.0.6) is automatically determined by the Multiroom cabling of the M230.

